


Installing VS-700C Stand-Alone Drivers on Windows XP

The VS-700C needs to be configured for “Stand-Alone Mode” to be used without the VS-700R I/O connected. Additionally, there is a separate driver that must be installed for the VS-700C to work properly in this mode.

To configure the VS-700C for stand-alone mode and install the VS-700C stand-alone drivers, do the following:

1. Locate the “Setting” area on the back of the VS-700C containing eight DIP switches. Carefully move DIP switch 1 to the “on” position (facing up). DIP switches 2-8 should be set to the default “off” position (facing down). See the following picture.



2. Disconnect all USB cables (except those for a USB keyboard and/or USB mouse, if used), then start up Windows.
3. Close all programs and any open windows. Disable any antivirus programs that could prevent or cause problems with driver installation.
4. Download the *VS700_Drivers.zip* folder from [here](#).
5. Extract the contents of the package by right-clicking on it and choosing "Extract All". **Note:** be sure to unzip it to a location on your computer that you can find later
6. In the extracted *VS700_Drivers* folder, open the folder for Windows XP
7. Open the *VS700C_stand_alone_drivers* folder
8. Locate the driver version you wish to install and extract its contents. Do this by right-clicking on the folder and selecting "Extract..." (Version 2.0.0 drivers will be indicated by a "v200" at the end of the folder name)
9. In the extracted folder, run *Setup.exe*. If prompted by the installer, run *Uninstall.exe* beforehand and restart your computer.
10. To begin the VS-700C Driver Setup installation, click the [Next] button.
11. Follow the on screen instructions in the VS-700C Driver Setup.

*If a dialog box regarding Windows logo testing appears, click [Continue Anyway].

12. The installer will prompt you to connect a USB cable from the VS-700C to your computer and to power on the VS-700C. Only do so when prompted by the installer.

13. After connecting the USB cable when prompted by the installer, a Found New Hardware Wizard dialog will appear. This may take a few minutes. When it appears, this window should look similar to the following picture.



14. Select "No, not this time" and then click [Next]
15. Verify that the New Hardware Wizard reads: "This wizard helps you install software for: VS-700C". Choose "Install the software automatically (Recommended)" and click [Next].



IMPORTANT: If the Wizard displays "UM-1" instead of "VS-700C", go back to step 1 and make sure your DIP switches are setup properly.

16. If a dialog box regarding Windows logo testing appears, click [Continue Anyway].
17. When the screen indicates "Completing the Found New Hardware Wizard", click [Finish].
18. The VS-700C Driver Setup will display a progress bar that says "Now Finishing Installation". When the VS-700C Driver Setup indicates "Installation has been completed", click the [Close] button.